

# DDInstal.ini file Details

EDDL™

The key to interoperability

- **There are two flavors of this.**

- Device file in Folders

- Used only by AMS Device Manager (version 1.0 to current).
    - Supports 1 to many devices in one install kit.

- Flat format (All files in the same folder)

- Supported by DeltaV
    - Supported by version 9.x and above
    - Only one device in each install kit.
    - The preferred / universal format for version 9.x and up.



EDDL™ COOPERATION TEAM

# DDInstal.ini file Details

- Layout of HART DDINSTAL.INI
- [Version]
- DD Version=2      // Does nothing in version 10.0 and above, just set it to 2
- FileVersion=2      // 1 = Hart only DDinstal.ini folder \ Manufacture ID Folder \ Device Type Folder
- // 2 = looks for protocol DDinstal.ini folder \ Manufacture ID Folder \ Device Type Folder (Use this option)
- [General]
- NumOfMfg=1      // Number of manufacturers in this ini file
- UseDeviceFileSubDirs=Yes      // If Yes, then use the folder structurer
- // \<Protocol>\<Mfg\_ID>\<Device\_Type>\ (AMS 6.5 and higher)
- // If No, then use the current folder to find //all the device files.
- // missing is the same as YES
- [Mfg1]      // First Manufacture.
- Protocol=HART      // Protocol for this Manufacturer's Device List
- Name=ABB      // Manufacturer name
- ID=00001a      // Six digit Manufacturer ID in hexadecimal
- NumOfDev=1      // Number of devices for this Manufacturer's Device List



# DDInstal.ini file Details

- [00001a.1] // Device Manufacture 1 (00001a)
- device 1 (.1)
- DevType=000c // Four digit Device Type ID in hexadecimal
- DevTypeDesc=65x // Device Type description (Only used for display during add device type)
- DevTypeRevDesc=Rev 1 // Device revision description (Only used for display during add device type)
- DevTypeRev=01 // Device revision in hexadecimal form
- DDRevDesc=DD Rev 1 // DD revision description (Only used for display during add device type)
- FMS=0101.FM<?> // Device fms, .fm6 or .fm8 file
- SYM=0101.sy<?> //Device sym file or sy<#> file
- MAP=0101.map //Device map file, used for Calibration



# DDInstal.ini file Details

- **ALM=00001a\_000c\_01.ALM** //Device alarm file (Used only by DeltaV 9.0 and higher, will be generated by add device type if missing)
- **FHX=00001a\_000c\_01.FHX** //Device fhx file (Used only by DeltaV 9.0 and higher, will be generated by add device type if missing)
- **DeviceHelp= ABC.PDF** //PDF device manual file that is accessed by the Help | Device on the right click context menu
- **BlockHelp=xxxx.chm** //context sensitive help file, .hlp, or .chm
- **OtherHelp=xxxx.hlp, yyyy.hlp** //Comma delimited list of files to copy for additional help
- **DeviceDll=abb\_65x.DLL** //Device Dll file
- **OtherDll=one.exe, temp.doc** //Comma delimited list of additional files to copy, used for the device ini file.
- **Template=abb\_65x.MRG** //Device mrg file
- **HART Protocol Rev=5** //Device HART Protocol revision
- **AmsVersionSupport=9.0, 10.0, 10.1** //Comma delimited list of supported AMS versions




# DDInstal.ini file Details

- Layout of a FF The way that FF Device Types are represented is shown below.
- The number of BlockDll### entries will vary depending on the number of blocks within the device. This file may or may not have values for the DeviceDll and BlockDll### entries depending if the Device Type has a .REG file or not.
- [Version]
- [Version]
- DD Version=2 // Does nothing in AMS 10.0, just set it to 2
- FileVersion=2 // 1 = Hart only DDInstal.ini folder \ Manufacture ID Folder \ Device Type Folder
- // 2 = looks for protocol DDInstal.ini folder \ Manufacture ID Folder \ Device Type Folder
- // Must use option 2 for FF devices
- [General]
- NumOfMfg=1 // Number of manufacturers in this ini file
- UseDeviceFileSubDirs=Yes // If Yes, then use the folder structurer
- // \<Protocol>\<Mfg\_ID>\<Device\_Type>\ (AMS 6.5 and higher )
- // <Mfg\_ID>\<Device\_Type>\ (AMS 1.0 to 6.2)
- // If No, then use the current folder to find //all the device files.
- // missing is the same as YES
- [Mfg1]
- Protocol=FF //Protocol for this Manufacturer's Device List
- Name=Rosemount Analytical //Manufacturer name
- ID=524149 //Six digit Manufacturer ID in hexadecimal form
- NumOfDev=1 //Number of devices for this Manufacturer's Device List
- [524149.1] // Manufacture ID. Device 1
- DevType=4084 //Four digit Device Type ID in hexadecimal form
- DevTypeDesc=4084C //Device Type description (Only used for display during add device type)
- DevTypeRevDesc=Rev 1 //Device revision description (Only used for display during add device type)



# DDInstal.ini file Details

- **DevTypeRev=01** //Device revision in hexadecimal form
- **DDRevDesc=DD Rev 1** //DD revision description (Only used for display during add device type)
- **FFO=0101.ffa** //Device ffo or ff5 file
- **SYM=0101.SYM** //Device sym or sy5 file
- **Template=524149\_4048\_01.MRG** //Device mrg file
- **MAP=0101.map** //Device map file
- **DeviceHelp=abcd.PDF** //PDF device manual file that is accessed by the Help | Device on the right click context menu
- **BlockHelp=xxxx.chm** //context sensitive help file, .hlp, or .chm
- **OtherHelp=xxxx.hlp, yyyy.hlp** //Comma delimited list of files to copy for additional help
- **DeviceDll=5081C\_Rev1.DLL** //Device Dll file – Contains the icon for the device if resource file based
- **BlockDll200=5081R\_Rev1.DLL** //Resource Block Dll
- **BlockDll300=5081\_Rev1.DLL** //Transducer Block Dll
- **BlockDll400=5081T\_Rev1.DLL** //Transducer Block Dll
- **BlockDll500=5081T2\_Rev1.DLL** //Transducer Block Dll
- **OtherDll=one.exe, temp.doc** //Comma delimited list of additional files to copy
- **AmsVersionSupport=7.0** //Comma delimited list of supported AMS versions



# DDInstal.ini file Details

- [Version]
- DD Version=2
- FileVersion=2
- 
- [General]
- NumOfMfg=1
- UseDeviceFileSubDirs=No
- 
- [Mfg1]
- Protocol=PROFIBUS-DP
- Name=Control Techniques
- ID=00008a
- NumOfDev=1



# DDInstal.ini file Details

- [00008a.1]
- DevType=0002
- DevTypeDesc=Commander SK
- DevTypeRevDesc=Rev 1
- DevTypeRev=01
- DDRevDesc=DD Rev 1
- PBO=8A\_2\_1\_1.pbo
- GSD=ctsk0672.gsd
- MAP=0002.map
- ALERT=00008A\_0002\_01.alert
- DeviceHelp=
- BlockHelp=
- OtherHelp=
- OtherDll=8A\_2\_1\_1.ini, ADBC.BMP
- Template=8A\_2\_1\_1.mrg
- AmsVersionSupport=11.0

